

MTS / T-BERD 4000V2 B192842 RELEASE NOTE

Firmware Pack Version B192842 (July 2019)

-	Boot	V10.38	12/April/2019
-	Linux Kernel	V10.54	18/March/2019
-	File System	V10.80	06/May/2019
-	Instrument Setup	V18.04	06/May/2019
-	Microscope	V18.04	06/May/2019
-	Fiber Optics	V18.08	11/July/2019

(This Fiber Optics release note supersedes the previous B191910 release note, with functions added with an * for this release)



CONTENT

CONTENT	2
T-BERD/MTS 4000V2 Base Unit	3
New functionalities	3
Improvements	3
OTDR	3
New functionalities	3
Improvements	3
FiberComplete	3
New functionalities	3
Improvements	
Scope	
New functionalities	3
Improvements	3



T-BERD/MTS 4000V2 Base Unit

New functionalities

- > New file manager user interface
- > Having a long press on the Result key moves from FO result to microscope function and vice versa
- > New handling of demo licences

Improvements

- > Now, direct possible access to EU StrataSync server link
- > In case of SAA use with wifi, the wifi autoconnect is always activated
- > Improved handling of auto IP via Ethernet cable
- > Improved handling of auto wifi connect in AP master mode
- > Improved management of wifi ad-hoc mode
- > Improved management of functions in the home page (in « single » mode, direction access to the function by pressing the icon
- > Improved cancelation of Result/Setup/File softkeys
- > Improved cursor positioning on the keyboard (now last position instead of always first character before)
- Improved keyboard for wifi password (more characters are available)
- > Improved management of file exchange via bluetooth or email
- > Improved management of file manager with many files
- > Improved 4000V2 management of functions in the home page
- > Improved management of Chinese characters for File/Setup/Result text (without white dots)
- > Improved management of SAA with wifi when the ethernet is set to a given predefined config without connection to an Ethernet cable
- > Improved upgrade menu when performing an upgrade from the boot menu

OTDR

New functionalities

New SmartTest user interface

Improvements

- > Correction of issue when moving from Expert SM OTDR to Expert MM OTDR function
- > Improved automatic measurements on short distance as well as on PON configurations
- > Improved handling of index of refraction for DWDM OTDR module
- > Improved management of channels for DWDM OTDR module
- > Improved automatic distance measurement of close reflective events
- > Expension table arrow no longer active in Smartlink view, only in trace view
- > Improved txt link manager file export access
- Improved automatic measurement with 1625nm MA2 OTDR modules *

FiberComplete

New functionalities

- Compatibility mode for FiberComplete version 1 and version 2
- > OTDR option of Fault finder FiberComplete option

Improvements

- > Improved management of link manager with cable view of FiberComplete
- > Improved handling of de-selection of FiberComplete during an FiberComplete cycle
- > Capability to perform bidirectional insertion loss only, without bidirectional ORL
- > Improved handling of fiber increment between units, this after manual storage

Scope

New functionalities

> Addition of the increment value on the microscope function

Improvements

- Improved management of microscope image, when the connector is not well centered (6K/8K)
- > Improved handling of microscope profiles at power down (remains at the next power up)



> Improved handling of the date format on the PDF report